

20. 12. 2022

[v] 6. 10. 83. 1281

[!] Fixed selection of a directory for storing logs

[!] Added ability to ignore ISO-9141 connections for cars before 2000

01. 10. 2022

[v] 6. 10. 82. 1281

[!] Fixed state of the "stop" button in a new session

[!] Fixed initialization of the table of error codes, which led to the expansion of service information.

[!] Stopping the session by the user is no longer accompanied by a preliminary warning about the loss of connection

09/27/2022

[v] 6. 10. 81. 1277

[!] Updated help

[-] Removed automatic adjustment of polling rate on charts

[!] Enabled ignoring the response of the commission for the conclusion of tests according to the old protocols

09/17/2022

[v] 6. 10. 80. 1271

[!] Added manual option for selecting a COM port for the adapter

[!] Changing the firmware of the MMC K-Line Advanced adapter

[!] The driver for the MMC K-Line Advanced adapter is included in the executable file

[-] Manual change of speed in charts is removed, only profit is left

[+] Added increased speed on the options tab

09/10/2022

[v] 6. 10. 79. 1256

[!] Fixed interface for Windows XP

[!] Fixed auto-detection of MMC K-Line Advanced adapter based on CH340 chip on Windows XP, Windows 7

[!] Bitrate search everywhere is done in descending order

04. 09. 2022

[v] 6. 10. 78. 1256

[!] Testing of the MMC K-Line Advanced adapter based on the CH9340 chip (designed to work on Windows 10 only)

[!] The logic for bypassing all possible bitrates - from higher to lower - has been changed for the MMC K-Line Advanced adapter

08/21/2022

[+] Added auto speed for charts

08/07/2022

[v] 6. 10. 77. 1217

[-] Disabled support for K-Line adapters of all types

[-] Disabled support for J2534 adapters

[-] Removed technical logging

[-] Checking for new versions has been abolished

[-] Removed sending technical information to developers

[-] Removed graphics performance check

[-] The built-in ability to update the software of MMC-Wireless adapters has been removed

[-] Exporting reports in MS Excel format has been removed

[!] The software is delivered as a single executable file and can be run from anywhere on the disk

[-] Removed control panel for protocol technical settings

; history.txt - version history file

; [+] - additions

; [!] - changes

; [v] - version