

1 04/13/2024
2 [c] 6.10.86.1301
3 [+] Increased polling interval for older control units, for example SRS IDECU 7000.
The maximum exchange rate with the unit is approximately 1 op/sec.
4 [+] For control units with a bitrate below 100 baud, the delay for communication is
300 ms
5 [+] Setting the exchange rate for protocols has been moved to the technical
parameters section. It is not recommended to change unless necessary.
6
7 03/31/2024
8 [c] 6.10.85.1298
9 [!DB] Correcting errors in the database
10 [+] Adding a control interval after reading identifiers via the MMC SCI protocol
11
12 04/27/2023
13 [c] 6.10.84.1294
14 [!] Russian language by default on first launch
15 [!DB] Fix in ABS error codes
16 [!] Correction of the time grid on charts
17
18 20.12.2022
19 [v] 6.10.83.1281
20 [!] Fixed selection of a directory for storing logs
21 [!] Added ability to ignore ISO-9141 connections for cars before 2000
22
23 01.10.2022
24 [v] 6.10.82.1281
25 [!] Fixed state of the "stop" button in a new session
26 [!] Fixed initialization of the table of error codes, which led to the expansion of
service information.
27 [!] Stopping the session by the user is no longer accompanied by a preliminary
warning about the loss of connection
28
29 09/27/2022
30 [v] 6.10.81.1277
31 [!] Updated help
32 [-] Removed automatic adjustment of polling rate on charts
33 [!] Enabled ignoring the response of the commission for the conclusion of tests
according to the old protocols
34
35 09/17/2022
36 [v] 6.10.80.1271
37 [!] Added manual option for selecting a COM port for the adapter
38 [!] Changing the firmware of the MMC K-Line Advanced adapter
39 [!] The driver for the MMC K-Line Advanced adapter is included in the executable file
40 [-] Manual change of speed in charts is removed, only profit is left
41 [+] Added increased speed on the options tab
42
43 09/10/2022
44 [v] 6.10.79.1256
45 [!] Fixed interface for Windows XP
46 [!] Fixed auto-detection of MMC K-Line Advanced adapter based on CH340 chip on
Windows XP, Windows 7
47 [!] Bitrate search everywhere is done in descending order
48
49 04.09.2022
50 [v] 6.10.78.1256
51 [!] Testing of the MMC K-Line Advanced adapter based on the CH9340 chip (designed to
work on Windows 10 only)
52 [!] The logic for bypassing all possible bitrates - from higher to lower - has been
changed for the MMC K-Line Advanced adapter
53
54 08/21/2022
55 [+] Added auto speed for charts
56
57 08/07/2022
58 [v] 6.10.77.1217
59 [-] Disabled support for K-Line adapters of all types
60 [-] Disabled support for J2534 adapters
61 [-] Removed technical logging
62 [-] Checking for new versions has been abolished

63 [-] Removed sending technical information to developers
64 [-] Removed graphics performance check
65 [-] The built-in ability to update the software of MMC-Wireless adapters has been removed
66 [-] Exporting reports in MS Excel format has been removed
67 [!] The software is delivered as a single executable file and can be run from anywhere on the disk
68 [-] Removed control panel for protocol technical settings
69
70 ;history.txt - version history file
71 ;[+] - additions
72 ;[!] - changes
73 ;[v] - version